## 0.1 Capturing Data

The image capture module is started by:

```
\$\ roslaunch\ logitech\_cam\ startup\_camera 2. launch
```

Commands are generated and logged by:

```
\ roslaunch logitech_cam logitech_cam_actuation.launch command_generator_args:="-c [[50,0,0],[-50,0,0]] -t 600 -f 1" outfile:="~/captureddata/onlypan600.raw.ba g"
```

This command will generate pan commands in each direction for 600 seconds and log the images and commands to the bag-file onlypan600.raw.bag

## 0.2 Pre Processing

The raw image stream is pre processed with pre\_processor.py. The following command gives an processed bag onlypan600.processed.bag with image size 160 time 120.

```
$ rosrun logitech_cam pre_processor.py -i /home/adam/onlypan600.raw.bag -o /home/adam/onlypan600.processed.bag -w 160 -h 120
```

To validate that the processing worked as it should, one can view the processed image streams by:

```
$ roslaunch logitech_cam show_processed.launch bagfile
:="/home/adam/onlypan600.processed.bag"
```

## 0.3 Learning

The learning is initialized by:

 $\$  rosrun logitech\_cam learner.py -i /home/adam/onlypan 600.processed.bag

## 0.4 Result




Figure 1: Diffeomorphism [500,0,0]




Figure 2: Diffeomorphism [-500,0,0]